
PureCMS™ 3

Installation Guide

by GlobalSCAPE Texas, LP

Table of Contents

Installing the included database and sample site.....	1
<i>Installation checklist.....</i>	<i>1</i>
<i>Installation procedure</i>	<i>2</i>
Installing with your own database and the sample site	4
<i>Installation checklist.....</i>	<i>4</i>
<i>Installation procedure</i>	<i>5</i>
Installing with your own site and the PureCMS database.....	7
<i>Installation checklist.....</i>	<i>7</i>
<i>Installation procedure</i>	<i>8</i>
Installing with your own site and your own database	10
<i>Installation checklist.....</i>	<i>10</i>
<i>Installation procedure</i>	<i>11</i>
Working as the Server Administrator	13
Publication options	14
Registering PureCMS.....	15

Installing the included database and sample site

Installation checklist

Use this list to prepare for installation and to quickly get PureCMS up and running.

- Make sure your system meets the requirements**
- Get software** – Download PureCMS.exe from <http://www.globalscape.com/downloads/purecms.asp>
- Prepare for the PureCMS database**
 - Make sure Microsoft SQL is not on your Staging Server
- Check email addresses**
 - Staging Server account has access to SMTP Server
 - Address where the Webmaster receives email
- Check access to Production Server**
- Check that you have your serial number**
- Check your IP address**
 - Non-standard port?
- Disable Anti-virus software**
- Install PureCMS**

Staging server system requirements

- Windows 2000 Workstation, Server, Advanced Server, Server 2003 or Windows XP Pro
- Microsoft IIS 5.0.2314.0 or higher
- 650 MHz PIII, at least, 1 GHz PIII recommended
- At least 128 MB RAM, 256 or more MB of RAM recommended
- A static IP address
- A TCP/IP network connection for users and if connecting to the Production Server via FTP
- An Internet connection for registration

Where to install PureCMS

You install PureCMS on a Staging Server. The Staging Server hosts your Web site for everyone who needs to make changes. It also tracks all changes to the Web site and manages all the PureCMS Webmaster and user accounts.

The Production Server hosts your Web site for the public on the World Wide Web and tracks your site statistics.

Checking for MicrosoftSQL on your Staging Server

1. Right-click on the **My Computer** icon.
2. Select **Manage**.
3. Double-click **Services and Applications**.
4. Double-click **Services**.
5. If **MSSQLSERVER** is in the list of services, you have Microsoft SQL on the machine.
6. You can either remove Microsoft SQL or you can install PureCMS with your own database (see installation instructions on page four or ten).

Installation procedure

1. Close all other programs, and disable any anti-virus software.
2. Double-click the PureCMS installation program you downloaded, or place your PureCMS CD in your CD-ROM drive. You may have to wait a few moments while it prepares to install. When the **PureCMS** welcome screen appears, click **Next**.
3. The **License Agreement** appears. Click **Yes** to accept the license agreement.
4. The **Registration** window opens. Enter your PureCMS **Serial Number**. The installation will automatically enter the first available **IP Address** for your Staging Server. If you have more than one IP address for the Staging Server, you can choose any one of them, but it must be a static IP address.
5. (Optional) If your Staging server uses a port other than 80 for Web connections, place a colon and the correct Web port number after the IP address. For example: 127.0.0.1:8080
6. The computer where you are installing must have an active connection to the Internet to complete the installation. Click **Next**.
7. If you are connected to the Internet and you typed your serial number correctly, you will see a successful registration message. Click **OK**.
8. The **Feature Selection** window opens.
 - **PureCMS** is the program. Keep this box checked.
 - **MSDE 2000** is Microsoft Data Engine, and installs a database for PureCMS. Keep this box checked. PureCMS also supports MySQL or Microsoft SQL. This will not be available if you already have an MS SQL database on the machine where you are installing. If you want to use MySQL or Microsoft SQL, use the installation guide that starts on page four, or the installation guide that starts on page ten.
 - The **Sample Web Site** is the Acme Consulting Web site used to demonstrate the program. Keep this box checked. Installing the sample Web site is recommended on first use for learning the PureCMS system.
9. Click **Next**.
10. The **Installation Location** window opens. Choose the folder where you will install the PureCMS program. The default location is C:\Program Files\GlobalSCAPE\PureCMS. Click **Browse** if you want to install in a different location. Click **Next**.
11. The **Mail Server Settings** window opens. You must enter the domain name or IP address for the **SMTP mail server** PureCMS will use to send e-mail messages. The Staging Server must be able to connect to this server without a username or password. Also enter an **E-mail Address**. PureCMS will send e-mail alerts from this address. Click **Next**.
12. The **Webmaster Account Login** window opens. Type a **Login** and **Password**, then type the password again exactly the same in **Confirm**. This will be the Webmaster account for PureCMS. This is the main account for operating and administering PureCMS. Click **Next**.
13. Another **Webmaster Account** window opens. Enter the **E-mail** address for the user of the account you just created. Click **Next**.
14. If you are installing PureCMS on a computer with only one virtual Web site, the installation will skip this step. If you are installing PureCMS on a computer with more than one virtual site in Microsoft Internet Information Services (IIS), the **Select Web Site** window opens. The install will display a list of IIS Web sites available on the computer. Choose a site from the list that will be available to any possible PureCMS user. Click **Next**.

15. The **IIS Virtual Folders Specification** window appears. In **Application Folder**, type a name for the virtual folder for the PureCMS program. The default is **/PureCMS**, but it can be any name you like, provided there are no spaces in the name. A new folder is recommended for the PureCMS application. If the virtual folder you chose does not already exist, the installer will create the virtual folder.
In **Staging Folder**, type a name (with no spaces) for the virtual directory of the sample site. It must be different than the name in **Application Folder**. The default is **/PureCMSSample**. If the virtual folder you chose does not already exist, the installer will create the virtual folder. If you plan to use absolute paths in your Web site, type just a forward slash (*/*) in **Staging Folder** to avoid problems when you publish your site. Click **Next**.
16. The **Setup Status** window opens. The PureCMS installation begins writing files to your hard drive. This may take several minutes.
17. The **InstallShield Wizard Complete** window opens. Choose **Yes, I want to restart my computer now**, and click **Finish** to complete the installation. You must restart to complete the installation.
18. When you reboot and log in to Windows, the InstallShield Wizard completes the installation, the release notes open, and the PureCMS program opens in your Web browser.
19. You may now re-enable your anti-virus software.

Installing with your own database and the sample site

Installation checklist

Use this list to prepare for installation and to quickly get PureCMS up and running.

- Make sure your systems meet the requirements**
- Get software** – Download PureCMS.exe from <http://www.globalscape.com/downloads/purecms.asp>
- Prepare the database**
 - Create a blank database in Microsoft SQL or MySQL
 - Get user name and password for database
 - Set to use SQL Authentication over TCP/IP
- Check email addresses**
 - Staging Server account has access to SMTP Server
 - Address where the Webmaster receives email
- Check access to Production Server**
- Check that you have your serial number**
- Check your IP address**
 - Non-standard port?
- Disable Anti-virus software**
- Install PureCMS**

Staging server system requirements

- Windows 2000 Workstation, Server, Advanced Server or Windows XP Pro
- Microsoft IIS 5.0.2314.0 or higher
- 650 MHz PIII, at least, 1 GHz PIII recommended
- At least 128 MB RAM, 256 or more MB of RAM recommended
- A static IP address
- A TCP/IP network connection for users and if connecting to the Production Server via FTP
- An Internet connection for registration

Where to install PureCMS

You install PureCMS on a Staging Server. The Staging Server hosts your Web site for everyone who needs to make changes. It also tracks all changes to the Web site and manages all the PureCMS Webmaster and user accounts.

The Production Server hosts your Web site for the public on the World Wide Web and tracks your site statistics.

Installation procedure

1. Create a blank database in MySQL or Microsoft SQL Server.
2. Create a user name for the database with at least one character. PureCMS will not accept a database with a blank user name.
3. Set the database to use TCP/IP connections (NOT named pipes).
4. Set the database to use SQL authentication (NOT Windows authentication).
5. Close all other programs, and disable any anti-virus software.
6. Double-click the PureCMS installation program you downloaded, or place your PureCMS CD in your CD-ROM drive. You may have to wait a few moments while it prepares to install. When the **PureCMS** welcome screen appears, click **Next**.
7. The **License Agreement** appears. Click **Yes** to accept the license agreement.
8. The **Registration** window opens. Enter your PureCMS **Serial Number**. The installation will automatically enter the first available **IP Address** for your Staging Server. If you have more than one IP address for the Staging Server, you can choose any one of them, but it must be a static IP address.
9. (Optional) If your Staging Server uses a port other than 80 for Web connections, place a colon and the correct Web port number after the IP address. For example: 127.0.0.1:8080.
10. The computer where you are installing must have an active connection to the Internet to complete the installation. Click **Next**.
11. If you are connected to the Internet and you typed your serial number correctly, you will see a successful registration message. Click **OK**.
12. The **Feature Selection** window opens. Make sure the MSDE 2000 check box is cleared, or does not appear.
 - **PureCMS** is the program. Keep this box checked.
 - **MSDE 2000** is Microsoft Data Engine, If you are using Microsoft SQL this will not be available. If the box is available, clear the box.
 - The **Sample Web Site** is the Acme Consulting Web site used to demonstrate the program. Keep this box checked. Installing the sample Web site is recommended on first use for learning the PureCMS system.
13. Click **Next**.
14. The **Installation Location** window opens. Choose the folder where you will install the PureCMS program. The default location is C:\Program Files\GlobalSCAPE\PureCMS. Click **Browse** if you want to install in a different location. Click **Next**.
15. The **Mail Server Settings** window opens. You must enter the domain name or IP address for the **SMTP mail server** PureCMS will use to send e-mail messages. The Staging Server must be able to connect to this server without a username or password. Also enter an **E-mail Address**. PureCMS will send e-mail alerts from this address. Click **Next**.
16. The **Webmaster Account Login** window opens. Type a **Login** and **Password**, then type the password again exactly the same in **Confirm**. This will be the Webmaster account for PureCMS. This is the main account for operating and administrating PureCMS. Click **Next**.
17. Another **Webmaster Account** window opens. Enter the **E-mail** address for the user of the account you just created. Click **Next**.

18. If you are installing PureCMS on a computer with only one virtual Web site, the installation will skip this step. If you are installing PureCMS on a computer with more than one virtual site in Microsoft Internet Information Services (IIS), the **Select Web Site** window opens. The install will display a list of IIS Web sites available on the computer. Choose a site from the list that will be available to any possible PureCMS user. Click **Next**.
19. The **IIS Virtual Folders Specification** window appears. In **Application Folder**, type a name for the virtual folder for the PureCMS program. The default is **/PureCMS**, but it can be any name you like, provided there are no spaces in the name. A new folder is recommended for the PureCMS application. If the virtual folder you chose does not already exist, the installer will create the virtual folder. In **Staging Folder**, type a name (with no spaces) for the virtual directory of the sample site. It must be different than the name in **Application Folder**. The default is **/PureCMSSample**. If the virtual folder you chose does not already exist, the installer will create the virtual folder. If you plan to use absolute paths in your Web site, type just a forward slash (/) in **Staging Folder** to avoid problems when you publish your site. Click **Next**.
20. The **Database Server Type** window appears. Choose the database that matches the one you will be using with PureCMS. Click **Next**.
21. The **Database Host and Name** window appears. In **Host Name**, enter the domain name or IP address of the computer where the database resides. In **Database Name**, enter the name of the database you created for PureCMS. Click **Next**.
22. The **Database Login Details** window appears. In **User**, enter the user name you created for the new database. In **Password**, type the password for the database. In **Retype**, enter the password again exactly the same.
23. The **Setup Status** window opens. The PureCMS installation begins writing files to your hard drive. This may take several minutes.
24. The **InstallShield Wizard Complete** window opens. Choose **Yes, I want to restart my computer now**, and click **Finish** to complete the installation. You must restart to complete the installation.
25. When you reboot and log in to Windows, the InstallShield Wizard completes the installation, the release notes open, and the PureCMS program opens in your Web browser.
20. You may now re-enable your anti-virus software.

Installing with your own site and the PureCMS database

Installation checklist

Use this list to prepare for installation and to quickly get PureCMS up and running.

- Make sure your systems meet the requirements**
- Get software** – Download PureCMS.exe from <http://www.globalscape.com/downloads/purecms.asp>
- Prepare for the PureCMS database**
 - Make sure Microsoft SQL is not on your Staging Server
- Check email addresses**
 - Staging Server account has access to SMTP Server
 - Address where the Webmaster receives email
- Check access to Production Server**
 - For FTP access – address, user name, password
 - For network access – proper and complete path names
- Check that you have your serial number**
- Check your IP address**
 - Non-standard port?
- Disable Anti-virus software**
- Install PureCMS**

Staging server system requirements

- Windows 2000 Workstation, Server, Advanced Server or Windows XP Pro
- Microsoft IIS 5.0.2314.0 or higher
- 650 MHz PIII, at least, 1 GHz PIII recommended
- At least 128 MB RAM, 256 or more MB of RAM recommended
- A static IP address
- A TCP/IP network connection for users and if connecting to the Production Server via FTP
- An Internet connection for registration

Where to install PureCMS

You install PureCMS on a Staging Server. The Staging Server hosts your Web site for everyone who needs to make changes. It also tracks all changes to the Web site and manages all the PureCMS Webmaster and user accounts.

The Production Server hosts your Web site for the public on the World Wide Web and tracks your site statistics.

Checking for MicrosoftSQL on your Staging Server

1. Right-click on the **My Computer** icon.
2. Select **Manage**.
3. Double-click **Services and Applications**.
4. Double-click **Services**.
5. If **MSSQLSERVER** is in the list of services, you have Microsoft SQL on the machine.
6. You can either remove Microsoft SQL or you can install PureCMS with your own database (see installation instructions on page four or ten).

Installation procedure

1. Close all other programs, and disable any anti-virus software.
2. Double-click the PureCMS installation program you downloaded, or place your PureCMS CD in your CD-ROM drive. You may have to wait a few moments while it prepares to install.
When the **PureCMS** welcome screen appears, click **Next**.
3. The **License Agreement** appears. Click **Yes** to accept the license agreement.
4. The **Registration** window opens. Enter your PureCMS **Serial Number**. The installation will automatically enter the first available **IP Address** for your Staging Server. If you have more than one IP address for the Staging Server, you can choose any one of them, but it must be a static IP address.
5. (Optional) If your Staging server uses a port other than 80 for Web connections, place a colon and the correct Web port number after the IP address. For example: 127.0.0.1:8080.
6. The computer where you are installing must have an active connection to the Internet to complete the installation. Click **Next**.
7. If you are connected to the Internet and you typed your serial number correctly, you will see a successful registration message. Click **OK**.
8. The **Feature Selection** window opens. Clear the **Sample Web Site** check box.
 - **PureCMS** is the program. Keep this box checked.
 - **MSDE 2000** is Microsoft Data Engine, and installs a database for PureCMS. Keep this box checked. PureCMS also supports MySQL or Microsoft SQL. This will not be available if you already have an MS SQL database on the machine where you are installing. If you want to use MySQL or Microsoft SQL use the installation guide that starts on page four, or the installation guide that starts on page ten.
 - Clear the **Sample Web Site** check box. This is the Acme Consulting Web site used to demonstrate the program.
9. Click **Next**.
10. The **Installation Location** window opens. Choose the folder where you will install the PureCMS program. The default location is C:\Program Files\GlobalSCAPE\PureCMS. Click **Browse** if you want to install in a different location. Click **Next**.
11. The **Mail Server Settings** window opens. You must enter the domain name or IP address for the **SMTP mail server** PureCMS will use to send e-mail messages. The Staging Server must be able to connect to this server without a username or password. Also enter an **E-mail Address**. PureCMS will send e-mail alerts from this address. Click **Next**.
12. The **Import Site** window opens, asking if you want to import an existing site. Select **Copy Files From Existing Site** and click **Next**.
13. The **Transfer Files** window opens, asking if you access your Web site via an **FTP Connection** or a **Network Mapped/Local Drive**. Select whichever is appropriate for you. Click **Next**.
14. If your Production Web site is on a mapped or local drive, skip to step sixteen. If you connect with your Production Web site via FTP, the **FTP Server Details** window opens. Enter the IP address or the FTP address of your Production Server in **IP Address**. If you make transfers over a port other than 21, change to the appropriate port in **Port**. Click **Next**.
15. The **FTP Server Login** window opens. In **User** enter your FTP username. Enter your FTP password in **Password**, then enter your password again in **Retype**. Click **Next**.

16. The **FTP Server Path** or **Local Path** window opens.
 - If your production site is on a mapped or local drive, click **Browse**, and browse to the drive and folder location of the Production Web site.
 - If your production site is on an FTP server, type the path to the site on the FTP server in **Server Path**. If your production site is at the root of your FTP site, type **/**.
17. Click **Next**.
18. The **Staging Location** window opens. Browse to the folder where you want to keep your Staging site. Click **Next**.
19. The **Webmaster Account Login** window opens. Type a **Login** and **Password**, then type the password again exactly the same in **Confirm**. This will be the Webmaster account for PureCMS. This is the main account for operating and administrating PureCMS. Click **Next**.
20. Another **Webmaster Account** window opens. Enter the **E-mail** address for the user of the account you just created. Click **Next**.
21. If you are installing PureCMS on a computer with only one virtual Web site, the installation will skip this step. If you are installing PureCMS on a computer with more than one virtual site in Microsoft Internet Information Services (IIS), the **Select Web Site** window opens. The install will display a list of IIS Web sites available on the computer. Choose a site from the list that will be available to any possible PureCMS user. Click **Next**.
22. The **IIS Virtual Folders Specification** window appears. In **Application Folder**, type a name for the virtual folder for the PureCMS program. The default is **/PureCMS**, but it can be any name you like, provided there are no spaces in the name. A new folder is recommended for the PureCMS application. If the virtual folder you chose does not already exist, the installer will create the virtual folder.
In **Staging Folder**, type a name (with no spaces) for the virtual directory of the sample site. It must be different than the name in **Application Folder**. The default is **/PureCMSSample**. If the virtual folder you chose does not already exist, the installer will create the virtual folder. If you plan to use absolute paths in your Web site, type just a forward slash (**/**) in **Staging Folder** to avoid problems when you publish your site. Click **Next**.
23. The **Setup Status** window opens. The PureCMS installation begins writing files to your hard drive. This may take several minutes.
24. When the installation finishes writing files to your hard drive, PureCMS begins importing your Web files. A Web browser window opens and shows the progress of the import. **DO NOT CLOSE THIS WINDOW** until the importation is complete. Once the import process has finished, you will see the message **Site Import has completed successfully**. Close the Web browser window.
25. The **InstallShield Wizard Complete** window opens. Choose **Yes, I want to restart my computer now**, and click **Finish** to complete the installation. You must restart to complete the installation.
26. When you reboot and log in to Windows, the InstallShield Wizard completes the installation, the release notes open, and the PureCMS program opens in your Web browser.
27. You may now re-enable your anti-virus software.

Installing with your own site and your own database

Installation checklist

Use this list to prepare for installation and to quickly get PureCMS up and running.

- Make sure your systems meet the requirements**
- Get software** – Download PureCMS.exe from <http://www.globalscape.com/downloads/purecms.asp>
- Prepare the database**
 - Create a blank database in Microsoft SQL or MySQL
 - Get user name and password for database
 - Set to use SQL Authentication over TCP/IP
- Check email addresses**
 - Staging Server account has access to SMTP Server
 - Address where the Webmaster receives email
- Check access to Production Server**
 - For FTP access – address, user name, password
 - For network access – proper and complete path names
- Check that you have your serial number**
- Check your IP address**
 - Non-standard port?
- Disable Anti-virus software**
- Install PureCMS**

Staging server system requirements

- Windows 2000 Workstation, Server, Advanced Server or Windows XP Pro
- Microsoft IIS 5.0.2314.0 or higher
- 650 MHz PIII, at least, 1 GHz PIII recommended
- At least 128 MB RAM, 256 or more MB of RAM recommended
- A static IP address
- A TCP/IP network connection for users and if connecting to the Production Server via FTP
- An Internet connection for registration

Where to install PureCMS

You install PureCMS on a Staging Server. The Staging Server hosts your Web site for everyone who needs to make changes. It also tracks all changes to the Web site and manages all the PureCMS Webmaster and user accounts.

The Production Server hosts your Web site for the public on the World Wide Web and tracks your site statistics.

Installation procedure

1. Create a blank database in MySQL or Microsoft SQL Server.
2. Create a user name for the database with at least one character. PureCMS will not accept a database with a blank user name.
3. Set the database to use TCP/IP connections (NOT named pipes).
4. Set the database to use SQL authentication (NOT Windows authentication).
5. Close all other programs, and disable any anti-virus software.
6. Double-click the PureCMS installation program you downloaded, or place your PureCMS CD in your CD-ROM drive. You may have to wait a few moments while it prepares to install. When the **PureCMS** welcome screen appears, click **Next**.
7. The **License Agreement** appears. Click **Yes** to accept the license agreement.
8. The **Registration** window opens. Enter your PureCMS **Serial Number**. The installation will automatically enter the first available **IP Address** for your Staging Server. If you have more than one IP address for the Staging Server, you can choose any one of them, but it must be a static IP address.
9. (Optional) If your Staging Server uses a port other than 80 for Web connections, place a colon and the correct Web port number after the IP address. For example: 127.0.0.1:8080.
10. The computer where you are installing must have an active connection to the Internet to complete the installation. Click **Next**.
11. If you are connected to the Internet and you typed your serial number correctly, you will see a successful registration message. Click **OK**.
12. The **Feature Selection** window opens. Clear the **MSDE 2000** check box.
 - **PureCMS** is the program. Keep this box checked.
 - **MSDE 2000** is Microsoft Data Engine, If you are using Microsoft SQL this will not be available. If the box is available, clear the box.
 - Clear the **Sample Web Site** check box. This is the Acme Consulting Web site used to demonstrate the program.
13. Click **Next**.
14. The **Installation Location** window opens. Choose the folder where you will install the PureCMS program. The default location is C:\Program Files\GlobalSCAPE\PureCMS. Click **Browse** if you want to install in a different location. Click **Next**.
15. The **Mail Server Settings** window opens. You must enter the domain name or IP address for the **SMTP mail server** PureCMS will use to send e-mail messages. The Staging Server must be able to connect to this server without a username or password. Also enter an **E-mail Address**. PureCMS will send e-mail alerts from this address. Click **Next**.
16. The **Import Site** window opens, asking if you want to import an existing site. Select **Copy Files From Existing Site** and click **Next**.
17. The **Transfer Files** window opens, asking if you access your Web site via an **FTP Connection** or a **Network Mapped/Local Drive**. Select whichever is appropriate for you. Click **Next**.
18. If your Production Web site is on a mapped or local drive, skip to step sixteen. If you connect with your Production Web site via FTP, the **FTP Server Details** window opens. Enter the IP address or the FTP address of your Production Server in **IP Address**. If you make transfers over a port other than 21, change to the appropriate port in **Port**. Click **Next**.
19. The **FTP Server Login** window opens. In **User** enter your FTP username. Enter your FTP password in **Password**, then enter your password again in **Retype**. Click **Next**.

20. The **FTP Server Path** or **Local Path** window opens.
 - If your production site is on a mapped or local drive, click **Browse**, and browse to the drive and folder location of the Production Web site.
 - If your production site is on an FTP server, type the path to the site on the FTP server in **Server Path**. If your production site is at the root of your FTP site, type **/**.
21. Click **Next**.
22. The **Staging Location** window opens. Browse to the folder where you want to keep your Staging site. Click **Next**.
23. The **Webmaster Account Login** window opens. Type a **Login** and **Password**, then type the password again exactly the same in **Confirm**. This will be the Webmaster account for PureCMS. This is the main account for operating and administrating PureCMS. Click **Next**.
24. Another **Webmaster Account** window opens. Enter the **E-mail** address for the user of the account you just created. Click **Next**.
25. If you are installing PureCMS on a computer with only one virtual Web site, the installation will skip this step. If you are installing PureCMS on a computer with more than one virtual site in Microsoft Internet Information Services (IIS), the **Select Web Site** window opens. The install will display a list of IIS Web sites available on the computer. Choose a site from the list that will be available to any possible PureCMS user. Click **Next**.
26. The **IIS Virtual Folders Specification** window appears. In **Application Folder**, type a name for the virtual folder for the PureCMS program. The default is **/PureCMS**, but it can be any name you like, provided there are no spaces in the name. A new folder is recommended for the PureCMS application. If the virtual folder you chose does not already exist, the installer will create the virtual folder.
In **Staging Folder**, type a name (with no spaces) for the virtual directory of the sample site. It must be different than the name in **Application Folder**. The default is **/PureCMSSample**. If the virtual folder you chose does not already exist, the installer will create the virtual folder. If you plan to use absolute paths in your Web site, type just a forward slash (**/**) in **Staging Folder** to avoid problems when you publish your site. Click **Next**.
27. The **Database Server Type** window appears. Choose the database that matches the one you will be using with PureCMS. Click **Next**.
28. The **Database Host and Name** window appears. In **Host Name**, enter the domain name or IP address of the computer where the database resides. In **Database Name**, enter the name of the database you created for PureCMS. Click **Next**.
29. The **Database Login Details** window appears. In **User**, enter the user name you created for the new database. In **Password**, type the password for the database. In **Retype**, enter the password again exactly the same.
30. The **Setup Status** window opens. The PureCMS installation begins writing files to your hard drive. This may take several minutes.
31. When the installation finishes writing files to your hard drive, PureCMS begins importing your Web files. A Web browser window opens and shows the progress of the import. **DO NOT CLOSE THIS WINDOW** until the importation is complete. Once the import process has finished, you will see the message **Site Import has completed successfully**. Close the Web browser window.
32. The **InstallShield Wizard Complete** window opens. Choose **Yes, I want to restart my computer now**, and click **Finish** to complete the installation. You must restart to complete the installation.
33. When you reboot and log in to Windows, the InstallShield Wizard completes the installation, the release notes open, and the PureCMS program opens in your Web browser.
34. You may now re-enable your anti-virus software.

Working as the Server Administrator

Log in as Server Administrator

The application resides on the Staging Server in the PureCMS virtual folder (unless you chose a different location during the install). For example, if your machine name is “smith”, the URL would be **http://smith/PureCMS/**.

The sample Web site is installed in the PureCMSSample virtual folder. It can be directly accessed from a browser. For example, if your machine name is “smith” the Web site can be accessed using the URL **http://smith/PureCMSSample**.

1. To start using PureCMS, open your Web browser and type the Staging server URL (**http://smith/PureCMS**) in the **Address** bar.
2. Enter **PureAdmin** as the **Username**.
3. Enter the **Password** that you created for the Webmaster in the **Webmaster Account** window of the installation.
4. You will be logged in as the Server Administrator.
5. Under **Site URL**, choose your site.
6. Under **Log In to Selected Site**, click **Log In**.

If you cannot access PureCMSSample from a Web browser

The sample site home page is named **index.html**. Microsoft IIS may not automatically recognize pages named **index.htm** or **index.html** as home pages.

1. On the Staging Server, right-click the **My Computer** icon and choose **Manage**.
2. Expand **Services and Applications** and **Internet Information Services** by clicking the plus sign adjacent to them.
3. Right-click **Default Web Site** and choose **Properties**. The **Default Web Site Properties** window appears.
4. Click the **Documents** tab, and then the **Add** button. The **Add Default Document** window appears.
5. Type **index.html**, and click **OK**.
6. Click **OK** again in the **Default Web Site Properties** window. The **Inheritance Overrides** window may appear. Click **OK** once more.

Publication options

Configure a site for publishing on the same system or a mapped network drive

1. Log on to PureCMS with the Webmaster account you created in the installation. This will take you directly to the **Start Page** for the site you just installed.
2. On the menu bar, click **Tools > Admin Options > Publishing Options**.
3. Under **Production Server**, choose **Local** from the **Server Type** list.
4. Type the **Path** to the Web site directory on the Production Server. (example; C:\inetPub\wwwroot)
5. Click **Ok**.
6. A message appears telling you the configuration has been saved. Click **Ok**.

Configure a site for publication at a remote location

1. Log on to PureCMS with the Webmaster account you created in the installation. This will take you directly to the **Start Page** for the site you just installed.
2. On the menu bar, click **Tools > Admin Options > Publishing Options**.
3. Under **Production Server**, choose **FTP** from the **Server Type** list.
4. Type the **Path** to the Web site directory on the Production Server. If you connect directly to the Web site directory, type **/**.
5. In **Server Name**, type the domain or IP address for the Production Server, do NOT include ftp:// in the domain name.
6. If the Production Server uses a port other than 21 for FTP transfers, type the correct port number in **FTP Port**.
7. Enter your **FTP Username** and **FTP User Password** for the Production Server account.
8. Click **Ok**. A message appears telling you the configuration has been saved.
9. Click **Ok** again.

Note

Publication requires a stable connection between the Staging Server and the Production Server, especially if you are publishing a large site, or a site with lots of large files.

Registering PureCMS

Registration takes place when you install PureCMS, whether you have a trial serial number or a purchased serial number. If you install with a trial serial number, you will have to re-register when you purchase the software.

To register PureCMS

1. Make sure your Internet connection is active during the installation.
2. Enter your serial number when prompted during the installation.
3. The installation program registers your software.

To change from a trial license to a purchased license

1. Make sure your Staging Server's Internet connection is active.
2. Log in to PureCMS as Server Administrator (see page 13).
3. If you cannot see **Site URL**, click **Web Sites**.
4. Under **Site URL**, choose the site you want to change.
5. Under **Modify the Serial Number of Selected Site**, click **Modify**. The **Modify Serial Number** window opens.
6. In **Serial No**, type the serial number you received when you purchased a full license.
7. Click **OK**. A message appears telling you registration was successful.
8. Click **OK** again.

To remove PureCMS from a computer

1. In Windows 2000, click **Start > Settings > Control Panel**. In Windows XP, click **Start > Control Panel**.
2. Double-click **Add/Remove Programs**.
3. Select PureCMS and click **Change/Remove**.
4. The PureCMS install program opens and presents you with two options; **Repair** and **Remove**.
5. Select **Remove** and click **Next**.
6. You will be asked if you are sure you want to remove PureCMS. Click **OK**.
7. PureCMS will be removed from the computer.